

REPORT WRITER / 250 Programming Manual

Manual Part No. 45251-90022

Microfiche No. 45251-99022



HP 250 Business System

Hewlett-Packard
General Systems Division
19447 Pruneridge Avenue, Cupertino, California 95014

Copyright by Hewlett-Packard Company 1980

Printing History

New editions of this manual will incorporate all material updated since the previous edition. Update packages may be issued between editions and contain replacement and additional pages to be merged into the manual by the user. Each updated page will be indicated by a revised date at the bottom of the page. Note that pages which are rearranged due to changes on a previous page are not considered revised.

The manual printing date and part number indicate its current edition. The printing date changes when a new edition is printed. (Minor corrections and updates which are incorporated at reprint do not cause the date to change.) The manual part number changes when extensive technical changes are incorporated.

August 1978 ... **First Edition**

April 1979 ... **Second Edition**: Revised pages: 2-3, 2-6, 2-14, 2-15, 2-16, 3-1, 4-3, C-1

June 1979...updated pages for O.S.2.D: 2-17, 3-1, 3-6, 4-7, A-2, A-6

NOTICE

The information contained in this document is subject to change without notice.

HEWLETT-PACKARD MAKES NO WARRANTY OF ANY KIND WITH REGARD TO THIS MATERIAL, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. Hewlett-Packard shall not be liable for errors contained herein or for incidental or consequential damages in connection with the furnishing, performance or use of this material.

Hewlett-Packard assumes no responsibility for the use or reliability of its software on equipment that is not furnished by Hewlett-Packard.

This document contains proprietary information which is protected by copyright. All rights are reserved. No part of this document may be photocopied, reproduced or translated to another program language without the prior written consent of Hewlett-Packard Company.

HP Computer Museum
www.hpmuseum.net

For research and education purposes only.

Table of Contents

Chapter 1: Introduction

Definitions	1-1
Syntax	1-2

Chapter 2: Report Description Statements

REPORT HEADER	2-1
PAGE HEADER	2-3
HEADER	2-4
REPORT TRAILER	2-5
PAGE TRAILER	2-6
TRAILER	2-7
BREAK WHEN	2-8
PAGE LENGTH	2-10
LEFT MARGIN	2-11
PAUSE AFTER	2-12
SUPPRESS PRINT FOR	2-12
SUPPRESS PRINT AT	2-13
PRINT DETAIL IF	2-14
GRAND TOTALS ON	2-15
TOTALS ON	2-16
REPORT EXIT	2-17
END REPORT DESCRIPTION	2-18

Chapter 3: Report Execution Statements

BEGIN REPORT	3-1
DETAIL LINE	3-2
TRIGGER BREAK	3-4
TRIGGER PAGE BREAK	3-5
NUMPAGE=	3-5
END REPORT	3-6
STOP REPORT	3-6

Chapter 4: Functions

AVG 4-1
TOTAL 4-2
NUMDETAIL 4-3
NUMBREAK 4-4
OLDCV 4-5
NUMPAGE 4-5
NUMLINE 4-6
LAST BREAK 4-6
RWINFO 4-7

Chapter 5: Execution Hierarchy 5-1

Chapter 6: Example Report Programs

Example 1 6-1
Example 2 6-3
Example 3 6-4

Appendix A: Summary of Statements and Functions

Description Statements A-1
Execution Statements A-4
Functions A-5

Appendix B: Error Messages B-1

Appendix C: Memory Requirements C-1

Introduction



The HP REPORT WRITER/250 System is a combination of statements and functions which aid the programmer in producing reports. Standard report features such as headings, page numbers, totals, averages and logical breaks can be programmed using Report Writer. The operations are broken into three distinct groups.

1. **Report Description Statements** – Described in Chapter 2. These statements appear in the report description section of a program. They describe the image of the report, including headings, breaks, trailing comments and page size.
2. **Report Execution Statements** – Described in Chapter 3, the statements appear anywhere within the program, although they are only executed when a report is active. They cause the report description statements to be evaluated and cause the report details to be printed.
3. **System Functions** – Described in Chapter 4, these functions are used to hold information about the report including totals, averages, the last break or detail executed, and the page and line numbers last written.

The Report Writer statements work together to produce a report. One statement will cause another statement to be executed which in turn may cause another to be executed. To understand the relationship between statements, you should read the entire manual. Later, when you understand Report Writer, you can use Appendix A for a quick reference to the syntax of individual statements.

Definitions

Some of the terminology used with Report Writer may be unfamiliar to you. Several terms are defined here for your understanding.

HEADER – A header is a description of a series of operations to perform at the time a new break level is begun. For example, when a new page is begun the header might print the report name at the top of the page.

TRAILER – A trailer is a description of a series of operations to perform at the end of the current break level after the break condition has been triggered. It is executed prior to the execution of the header routine for the new break level. For example, when a page break occurs, the trailer might print the page number at the bottom of the page before printing the heading for the new page.

BREAK – A break is caused by a change in the value of one of the variables. You define this variable and the change required to the Report Writer. A break indicates special action is to take place. For example, assume you specify 60 lines to a page. When the Report Writer is about to output the 61st line, a break will occur.

LEVEL – Level is the means of establishing a hierarchical order to the report breaks. The highest level number represents the most frequent breaks and the lowest level number represents the least frequent breaks. For example, in a payroll report the highest level break might be a department and the lowest level be a division. There are nine possible levels, one being the lowest and nine being the highest.

DETAIL LINE – A detail line is the lowest logical group of data in a report. For example, in an inventory report the detail line is the output associated with a particular item (i.e., part number, description, quantity, etc.). The detail line is the primary trigger for all report breaks.

BLOCK STATEMENTS – These statements follow a header or trailer statement. They may be thought of as a subroutine automatically invoked by a break condition. The end of the block is indicated by the next execution of a Report Writer header, trailer or end statement.

The **PRINT USING** statement is not a specific Report Writer statement. However, its syntax is similar to many of the output statements in Report Writer. It is therefore very important that you have a thorough understanding of **PRINT USING** and **IMAGE** as described in the output chapter in the BASIC Programming Manual.

Syntax

The statements in this manual use the same syntax conventions as in the BASIC Programming Manual.

DOT MATRIX – All words and characters in dot matrix must appear as shown.

[] – All parameters in brackets are optional. If there are brackets within brackets, the parameter within the inner bracket may only be specified if the parameter in the outer bracket is specified.

{ } – One parameter must be selected from the parameters stacked within braces.

CHAPTER 2

Report Description Statements

All the statements in this chapter must be in a program section that begins with the REPORT HEADER statement and ends with the END REPORT DESCRIPTION statement. This block or group of statements may be anywhere within the program. If more than one report is to be written, several description blocks can be within the program.

During execution of the program, when the REPORT HEADER statement is read, the system looks for the END REPORT DESCRIPTION statement and skips execution to the statement following it. Therefore, a branching statement is not required before the report description section.

In Chapter 6, an example report program and resultant report are given. Many of the examples are taken from this report. Note that the example is on a fold-out page to allow for better referencing while you read.

The REPORT HEADER Statement

The REPORT HEADER statement has two purposes. The first is to indicate the beginning of the report description section. The second is to write a one-time heading on the first page of the report. The header is printed when the first DETAIL LINE, TRIGGER PAGE BREAK or TRIGGER BREAK statement is executed. (These statements are described in Chapter 3.) It is printed before the first PAGE HEADER.

The syntax of this statement is:

```
[label:]REPORT HEADER [WITH number LINES][USING { line id } [; list]]  
[block statements]          { image string }
```

The parameters for this statement are defined as follows:

label This is the standard BASIC line label. This label is referred to in the BEGIN REPORT statement. If not used, the BEGIN REPORT statement must refer to the line number of the REPORT HEADER statement.

- number The number of lines required for the header. If not entered, the value of number defaults to 1.
- line id A line number or label referencing an IMAGE statement.
- image string A list of image specifiers describing the output format, and enclosed in quotes.
- list This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced.
- block statements Statements may follow the REPORT HEADER statement. They will be evaluated and executed immediately after the HEADER statement.

Some examples of this statement follow.

```
60 Inv:  REPORT HEADER USING R_head
:
:
600 R_head:  IMAGE 20X,"XYZ COMPANY INVENTORY",2/
```

The initial heading (XYZ COMPANY INVENTORY) is printed beginning at column 21. Two blank lines follow. The BEGIN REPORT statement (described in Chapter 3) may reference line 60 or label Inv.

```
20  REPORT HEADER
```

With no block statements, there is no initial heading. The BEGIN REPORT statement must reference line 20.

```
20 Inv:  REPORT HEADER USING "20X,K,2/";"XYZ COMPANY
INVENTORY"
```

This example does exactly the same thing as the first example.

The PAGE HEADER Statement

The PAGE HEADER statement defines what is to be done at the top of each page. It is triggered by a page break condition. The syntax is:

```
PAGE HEADER [WITH number LINES] [USING { line id  
image string } [list]]  
[block statements]
```

The parameters are:

- | | |
|------------------|---|
| number | The number of lines required for the header. If not entered, the value of number defaults to 1. The number is evaluated during execution of the BEGIN REPORT statement. The number of lines for the PAGE HEADER and the PAGE TRAILER are used in conjunction with PAGE LENGTH to determine the effective page size. |
| line id | A line number or label referencing an IMAGE statement. |
| image string | A list of image specifiers describing the output format and enclosed in quotes. |
| list | This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced. |
| block statements | Statements may follow the PAGE HEADER statement. They will be evaluated and executed immediately after the PAGE HEADER statement. |

An example of this statement follows.

```
130 PAGE HEADER USING P_head;Date$  
140 PRINT USING P_2hd  
:  
:  
620 P_head:IMAGE 60X,8A,2/,10X,"PART",9X,"QUANTITY",10X,"UNIT",/,BX,  
"NUMBER",BX,"ON HAND",9X,"PRICE",BX,"VALUE"  
630 P_2hd: IMAGE 9X,"====",BX,"=====",BX,"====",BX,"===="
```

Since two program lines of image specifiers are needed to show the format, the PAGE HEADER statement refers to the first line (P_head) and the PRINT USING statement, which is the "block statement", refers to the second line (P_2hd).

The results of this example is shown in Chapter 6 "Example Report Program".

The HEADER Statement

The HEADER statement defines what is to be done as a heading routine for a specified break condition. Each HEADER statement is directly associated with a break condition. There may be only one active HEADER statement for each of the nine possible break levels.

```
HEADER level [WITH number LINES] [USING { line id  
[block statements]                { image string } [; list] ]
```

The parameters are:

level	A numeric expression evaluating to an integer from 1 to 9. This integer associates the header to a break condition. If level is 0, the HEADER statement will be ignored.
number	The number of lines required for the header. If not entered, the value of number defaults to 1. The number is evaluated every time the HEADER statement is executed and can be dynamically changed.
line id	A line number or label referencing an IMAGE statement.
image string	A list of image specifiers describing the output format and enclosed in quotes.
list	This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced.
block statements	Statements may follow the HEADER statement. They will be evaluated and executed immediately after the HEADER statement.

Some examples of this statement follow.

```
170  HEADER 1  
180      TOTALS ON Qty*Price  
190      PRINT USING P_head1;Div$  
:  
:
```

The TOTALS ON statement is described later in this chapter.

```
220  HEADER 3 USING P_head3  
230      TOTALS ON Qty*Price  
:  
:  
710  P_head3:  IMAGE /
```

The REPORT TRAILER Statement

The REPORT TRAILER statement is used to print a one-time trailer just prior to report termination. It is invoked by execution of the END REPORT statement, and is executed after all TRAILERS but prior to the last PAGE TRAILER.

```
REPORT TRAILER [WITH number LINES][USING { line id  
[block statements] image string } [list]]
```

The parameters are:

- number The number of lines required for the trailer. If not entered, the value of number defaults to 1. If the report trailer requires more than one line, it is important that this parameter be used to ensure that the trailer be printed on one page. If a page break occurs in the middle of a trailer, an error will occur.
- line id A line number or label referencing an IMAGE statement.
- image string A list of image specifiers describing the output format and enclosed in quotes.
- list This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced.
- block statements Statements may follow the REPORT TRAILER statement. They will be evaluated and executed immediately after the TRAILER statement.

An example of this statement follows:

```
160 REPORT TRAILER WITH 5 LINES USING R_trail;TOTAL(0,1),TOTAL(0,1)/NUMBREAK(1)  
170 PRINT USING R_2tr;AVG(0,1)  
:  
:  
650 R_trail1: IMAGE 2/,22X,"TOTAL COMPANY",10X,DCDDDCDDDPDD,/,22X,"AVG PER "  
"DIVISION",7X,DCDDDCDDDPDD  
656 R_2tr: IMAGE 22X,"AVG PER ITEM",11X,DDDCDDDPDD
```

The TOTAL, NUMBREAK, and AVG functions are described in Chapter 4.

The PAGE TRAILER Statement

The PAGE TRAILER statement defines the course of action to be taken at the bottom of each page. It is triggered by a page break condition.

```
PAGE TRAILER [WITH number LINES] [USING { line id  
[block statements]                {image string} [ : list] ]
```

The parameters for this statement are defined as follows:

- number The number of lines required for the trailer. If not entered, the value of number defaults to 1. If the page trailer requires more than one line, it is important that this parameter be used to ensure correct page alignment. The number is evaluated during execution of the BEGIN REPORT statement. The number of lines for the PAGE HEADER and the PAGE TRAILER are used in conjunction with PAGE LENGTH to determine the effective page size.
- line id A line number or label referencing an IMAGE statement.
- image string A list of image specifiers describing the output format and enclosed in quotes.
- list This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced.
- block statements Statements may follow the PAGE TRAILER statement. They will be evaluated and executed immediately after the PAGE TRAILER statement.

An example of this statement follows.

```
150 PAGE TRAILER WITH 2 LINES USING P_trail;NUMPAGE  
:  
:  
650 P_trail: IMAGE 60X,"PAGE",X,2D
```

This page trailer only requires one line but an extra blank line will follow because two lines are reserved by the WITH 2 LINES parameter. The NUMPAGE function is described in Chapter 4.

The TRAILER Statement

The TRAILER statement defines what is to be done as a follow up operation for a specified break condition. Each TRAILER statement is directly associated with a break condition. There may be only one active TRAILER statement for each of the nine possible break levels.

```
TRAILER level [WITH number LINES] [USING { line id  
image string } [ : list ] ]  
[block statements]
```

The parameters are:

- level A numeric expression evaluating to an integer from 0 to 9. This integer associates the trailer to a break level.
- number The number of lines required for the trailer. If not entered, the value of number defaults to 1. If the trailer requires more than one line, it is important that this parameter be used to ensure that a page break does not occur in the middle of the trailer. If a page break occurs in the middle of a trailer (because the maximum number of lines per page has been printed), an error will result. The number is evaluated every time the TRAILER statement is executed and can be dynamically changed.
- line id A line number or label referencing an IMAGE statement.
- image string A list of image specifiers describing the output format and enclosed in quotes.
- list This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced.
- block statements Statements may follow the TRAILER statement. They will be evaluated and executed immediately after the TRAILER statement.

Some examples of this statement follow.

```
200 TRAILER 1 USING P_trail1;OLDCV$(1),TOTAL(1,1)  
:  
:  
690 P_trail1: IMAGE "TOTAL",X,2A,X,"DIVISION",26X,DDDCDDDCDDDPDD
```

The OLDCV\$ and TOTAL functions are described in Chapter 4. This trailer only requires one line, so the WITH...LINES parameter is not entered.

```
240 TRAILER 3 WITH 2 LINES USING P_trail3;OLDCV(3),TOTAL(3,1)  
:  
:  
730 P_trail3: IMAGE /,"TOTAL DEPT",X,2A,29X,DDDCDDDCDDDPDD
```

This trailer requires two lines as stated in line 240. If it were not stated and a page break occurred after the first line was printed, an error would occur.

The BREAK WHEN Statement

The BREAK WHEN statement establishes the criteria for determining the level break condition. This break, in turn, will invoke the break condition for any higher numbered levels. While active, a break condition will trigger execution of the appropriate header/trailer statement blocks. There may only be one active BREAK WHEN statement for each of the nine possible break levels.

`BREAK level WHEN control CHANGES [BY increment]`

The parameters are:

- level** A numeric expression evaluating to an integer from 0 to 9. This break level associates the BREAK WHEN statement to header/trailer statement. If level is 0, the BREAK WHEN statement will be ignored.
- control** A numeric or string variable or expression evaluated during execution of the DETAIL LINE statement which is used to trigger the break condition.

A specific amount of space is reserved for a string expression control. If the string expression has a current length of greater than zero at execution of the BEGIN REPORT statement, this length is used. Otherwise, a default length of 18 will be used. For string variable controls, the dimensioned length will always be used. If that length is exceeded during the execution of the Report Writer, an error will occur.
- increment** A numeric expression evaluated at the execution of the BEGIN REPORT statement which establishes the incremental change necessary in control to trigger the break condition. The increment parameter may only be used for a numeric control. If not present, any change will trigger the break condition. The value of increment is rounded to the nearest integer (i.e., .01 becomes 0 which will cause an error; 1.6 becomes 2 and 2.1 becomes 2).

The break limit is set when the control variable is first given a value. The value of the increment parameter is multiplied by an integer such that it is just larger (or just smaller if increment is negative) than the value of the control variable. For example, if increment = 10 and the control variable = 27, then increment is multiplied by 3 for a break limit of 30. If increment is -10 and control is 5, then the break limit is 0.

Once the break limit is set, it does not change until after a break occurs. (A break occurs either because the control variable changes past the increment, or because a TRIGGER BREAK statement was executed.) The break limit changes by a multiple of the increment value so that it is just larger (or smaller) than the value of the control variable.

Examples of this statement follow.

```
100 BREAK 1 WHEN Div$ CHANGES
110 BREAK 3 WHEN Dept$ CHANGES
:
:
460 Div$=C$[1,2]
470 Dept$=C$[3,4]
```

Lines 460 and 470 are not in the description section.

```
200 BREAK 2 WHEN Dim CHANGES BY 10
```

If the value of Dim is initially 4, a break will occur when the value of Dim is equal to or greater than 10.

```
300 BREAK 4 WHEN Sam CHANGES BY 2
```

If the value of Sam is initially 5 then changes to 1, no break will occur. When the value changes to 6 or greater, a break will occur.

```
400 BREAK 5 WHEN Alpha CHANGES BY -1
```

If the initial value of Alpha is 3 then the value changes to 2 or less, a break will occur.

The PAGE LENGTH Statement

The PAGE LENGTH statement sets the vertical size of the page. The number of blank lines to appear at the top or bottom of the page may optionally be established. To arrive at effective or usable page size, subtract the total number of blank lines plus the number of lines required for the page header and page trailer from the lines per page. The result must be greater than three. All expressions are evaluated at the time of the BEGIN REPORT statement's execution.

```
PAGE LENGTH lines per page [ : blank lines top : blank lines bottom ]
```

The parameters are:

- | | |
|--------------------|--|
| lines per page | The number of lines per page. If not entered, it defaults to 66 lines with two blank lines at the top and bottom of the page. If lines per page evaluates to zero, no blanks are printed at the top or bottom of a page, a page heading is printed when the first detail line is executed, a page trailer is printed with the END REPORT, the user is responsible for invoking all page breaks by using the TRIGGER PAGE BREAK statement and the NUMLINE function will accumulate the number of lines printed up to 32767. |
| blank lines top | The number of blank lines to be output at the top of every page. The default is 2. The maximum is 255. |
| blank lines bottom | The number of blank lines to be output at the bottom of every page. The default is 2. The maximum is 255. |

The LEFT MARGIN Statement

The LEFT MARGIN statement may be used to horizontally shift a report on a page. It establishes the leftmost column of a line which may be used for printing. This statement only applies when output is going to a printer. For reports going to a CRT display, the left margin will always be 1.


LEFT MARGIN column

The parameter is:

column A numeric expression which evaluates to an integer from 1 to the current printer width less one (or 132, whichever is less). It defines the leftmost column from which to reference all image execution. The value of column -1 will be added to the length of each printed line. If LEFT MARGIN is not present, column defaults to 1.



The PAUSE AFTER Statement

The PAUSE AFTER statement temporarily pauses the execution of the report, allowing either the printing of reports on individual pages or viewing on the display. To resume execution of the report, you must press the  key.

```
PAUSE AFTER number PAGES
```

The parameter is:

number A numeric expression which evaluates to an integer between 0 and 32767. If evaluated to be zero, the PAUSE AFTER will have no effect.

The statement PAUSE AFTER 1 PAGES causes one page to print followed by a pause, the next page to print followed by a pause, etc.

The SUPPRESS PRINT FOR Statement

The SUPPRESS PRINT FOR statement provides a means of inhibiting print for a specified number of pages at the beginning of a report. Its primary purpose is to provide for restart in case of power or mechanical printer failures. Note that it is still necessary to rerun the report from its beginning so that totals may be accumulated correctly even though printout will not appear for the specified number of pages.

The SUPPRESS PRINT FOR statement performs its execution by altering the select code for the standard printer as set in the PRINTER IS statement. Use of the PRINTER IS statement while a report is active will cause an error 270 to occur.

```
SUPPRESS PRINT FOR number PAGES
```

The parameter is:

number A numeric expression evaluating to a positive integer. If set to 0, the statement is ignored.

The SUPPRESS PRINT AT Statement

The SUPPRESS PRINT AT statement allows reports to be produced at summary levels. Headers and trailers for levels lower than the SUPPRESS PRINT AT level are executed. Those with equal or higher levels are not. Except for the printout reduction, the report is produced exactly as if all details were being printed (i.e., the detail line must still be executed). Only one SUPPRESS PRINT AT statement may appear in a report description.

SUPPRESS PRINT AT level

The parameter is:

level A numeric expression evaluating to an integer from 1 to 9. Only headers and trailers with a lower level will be executed.

An example of this statement follows.

```
220 SUPPRESS PRINT AT 4
```

The headers and trailers with levels 1, 2 and 3 are printed. No detail lines are printed. Headers and trailers with levels 4 through 9 are not printed. Page headers and page trailers are not affected. Example 2 in Chapter 6 shows a report with the SUPPRESS PRINT AT statement used.

The PRINT DETAIL IF Statement

The PRINT DETAIL IF statement allows printing conditions for detail lines to be specified without affecting the totaling functions.

```
PRINT DETAIL IF conditional exp
```

The parameter is:

conditional exp	An expression which will evaluate to zero if false. Otherwise, it will be assumed to be true. It is evaluated at every execution of the DETAIL LINE statement and if zero, the printout for that line will be suppressed. The line's data, however, will be included in all totaling functions.
-----------------	---

If the DETAIL LINE statement requires more than 180 characters (including non-printing characters) to be defined, use a DETAIL LINE 0 to continue the statement. This will ensure that a PRINT DETAIL IF statement will execute correctly.

Some examples of this statement follow.

```
70 PRINT DETAIL IF Amt>200
```

When the DETAIL LINE is encountered, the variable Amt is evaluated. If Amt is greater than 200, the detail line is printed.

```
90 PRINT DETAIL IF Security<10
```

If the variable Security is equal or greater than 10, the detail line is not printed.

The GRAND TOTALS ON Statement

The GRAND TOTALS ON statement provides a means of having the Report Writer do automatic totaling for the entire report. The GRAND TOTALS ON statement may only appear once, directly following the REPORT HEADER statement. Once executed, the GRAND TOTALS ON statement allows two special functions to be used: TOTAL and AVG (described in Chapter 4). All totals are zero at the beginning of the report execution and are accessible at any time while the report is active. Totals are incremented during the execution of a DETAIL LINE 1-9 after all breaks are serviced but before control is passed to the USING part of the statement.

```
GRAND TOTALS ON exp1[, exp2...]
```

The parameter is:

exp Any valid number variable or expression.

An example of this statement follows.

```
60 Inv: REPORT HEADER  
70      GRAND TOTALS ON Qty,Qty*Price
```

Each time a DETAIL LINE statement (with a number of 1 through 9) is encountered the values of Qty and Qty*Price are added to the totals kept by the GRAND TOTALS ON statement.

The TOTALS ON Statement

The TOTALS ON statement provides a means of having the Report Writer do automatic totaling. The TOTALS ON statement may only appear within a header statement block and additionally must immediately follow the header statement. Only one TOTALS ON statement may be present in a header statement block. Once executed, the TOTALS ON statement allows two special functions to be used: TOTAL and AVG (described in Chapter 4). Totals are incremented during the execution of a DETAIL LINE (1-9) statement after all breaks are serviced but before control is passed to the USING part of the statement. Totals are zeroed before control is passed to their associated HEADER but they remain available and unchanged in all TRAILERS when a level break occurs.

```
TOTALS ON exp1[ , exp2...]
```

The parameter is:

exp Any valid numeric variable or expression.

An example of this statement follows.

```
170  HEADER 1
180  TOTALS ON Qty*Price
:
:
220  HEADER 3
230  TOTALS ON Qty*Price,Qty
```

The TOTALS ON statement keeps a running total of Qty*Price beginning when HEADER 1 is first executed and resetting each time thereafter at each execution of HEADER 1. The statement in line 230 keeps the same total and a running total of Qty but is governed by HEADER 3.

The REPORT EXIT Statement

The REPORT EXIT statement defines what action is to be taken when a report is prematurely stopped. It is triggered by the execution of a STOP REPORT statement in the local program. After the REPORT EXIT section is completed, blank lines are printed to ensure that a complete page is ejected.

```
REPORT EXIT (exec flag) [WITH number LINES] [USING { line id  
image string } [ : list ] ]  
[block statements]
```

The parameters are:

- | | |
|------------------|---|
| exec flag | An integer expression which is evaluated after the STOP REPORT is executed. If it evaluates to zero, the REPORT EXIT will not be executed. If it evaluates to any non-zero value, the REPORT EXIT will be performed. |
| number | The number of lines required for the exit routine. If not entered, the value of number defaults to 1. If the routine requires more than one line, it is important that this parameter be used to ensure correct page alignment. |
| line id | A line number or label referencing an IMAGE statement. |
| image string | A list of image specifiers describing the output format and enclosed in quotes. |
| list | This may be a list of string, numeric or array variables, literals, constants or expressions to be printed according to the image referenced. |
| block statements | Statements may follow the REPORT EXIT statement. They will be evaluated and executed immediately after the REPORT EXIT statement. |

An example of this statement follows:

```
100 REPORT EXIT (NUMLINES(0)>0) WITH 2 LINES USING "/,20X,K"  
;" *** USER TERMINATED REPORT ***"  
110 END REPORT DESCRIPTION  
:  
:  
200 ON KEY #8 "EXIT REPORT" GOTO Rexit  
:  
:  
300 Rexit: OFF KEY #8  
310 STOP REPORT  
320 GOTO Eoj
```


The END REPORT DESCRIPTION Statement

The END REPORT DESCRIPTION statement's purpose is to terminate the report description section begun by a REPORT HEADER statement. It is required for all reports.

The syntax for this statement is:

```
END REPORT DESCRIPTION
```

Report Execution Statements

The execution statements, beginning with `BEGIN REPORT` and ending with `END REPORT`, activate the report. Execution statements, with the exception of `STOP REPORT`, may only be executed in the program that initiated the current report by executing a `BEGIN REPORT` statement.

In Chapter 6 an example report program and resultant report are given. Many of the examples are taken from this report. Note that the example is on a fold out page to allow for better referencing while you read.

The `BEGIN REPORT` Statement

The `BEGIN REPORT` statement initiates execution. When executed, the Report Writer scans the report description section referenced by this statement and evaluates the non-dynamic report options in the section. If no errors are detected, all Report Writer system variables and controls are established. Only the variables which can change during the report execution are evaluated later (such as `PRINT DETAIL IF` condition, or header and trailer `WITH` number `LINES` parameters). Only one report may be active at a time.

```
BEGIN REPORT line id
```

The parameter is:

line id The line identifier (line number or line label) referencing a `REPORT HEADER` statement.

The DETAIL LINE Statement

The DETAIL LINE statement is the foundation around which the Report Writer runs. When the DETAIL LINE statement is executed, all break conditions are tested and triggered if appropriate before any output associated with the DETAIL LINE is printed. In addition, this statement causes all totals to be incremented. Upon the first execution of the DETAIL LINE statement, the Report Writer triggers the report header, page header and all header statements in ascending level-number sequence.

```
DETAIL LINE line [WITH number LINES][USING { line id  
image string }[#list]]
```

The parameters are:

- line A numeric expression evaluating to an integer between 0 and 9. If greater than zero, totals are incremented, Report Writer counters are incremented and a check for break conditions is made. If equal to zero, the above items are not done. If a DETAIL LINE statement will not fit on two program lines, a second DETAIL LINE statement can be used by setting the line parameter equal to one (or greater) in the first statement and equal to 0 in the second statement.
- number The number of lines required for output. If not entered, the value defaults to 1. If more than one line is required, it is important to enter the number so that a page break does not occur which would cause an error.
- line id A line number or label referencing an IMAGE statement.
- image string A string that contains an image format.
- list A list of numeric, string or array variables, constants, literals or expressions to be printed according to the image referenced.

Examples of this statement follow.

```
520 DETAIL LINE 1 USING D_line;Part$,Qty,Price,Qty*Price
.
.
770 D_line: IMAGE 9X,8A,8X,DCDDD,5X,DDCDDDPDD,3X,DDDCDDDPDD
```

This example causes the values of Part\$, Qty, Price and Qty*Price to be printed in the format shown.

```
100 DETAIL LINE 1
110 IF A=1 THEN GOTO X
120 IF A=2 THEN GOTO Y
130 IF A=3 THEN GOTO Z
.
.
200 X: DETAIL LINE 0 USING D1;A,B,C,D
.
.
300 Y: DETAIL LINE 0 USING D2;A,B,C,D
.
.
400 Z: DETAIL LINE 0 USING D3;A,B,C,D
```

In this example, all break conditions are checked and totals incremented at line 100, but no detail is output. The value of A determines the image used for the detail line. Line 200, 300, or 400 is used to print the line. When it is printed, totals are not incremented nor are break conditions checked.

The TRIGGER BREAK Statement

The TRIGGER BREAK statement provides a means of forcing a break condition that cannot be described with a BREAK WHEN statement. The break condition is treated in the same manner as if the control in the BREAK WHEN statement had invoked the break condition. The TRIGGER BREAK statement may not be executed while a level or page break is active.

TRIGGER BREAK level

The parameter is:

level A numeric expression evaluating to an integer from 1 to 9. This number associates the TRIGGER BREAK to BREAK WHEN, header and/or trailer statements of the same level. All trailer and header statements with greater or equal levels are triggered. Refer to Chapter 5, Execution Hierarchy, for the order each statement is triggered.

The TRIGGER PAGE BREAK Statement

The TRIGGER PAGE BREAK statement allows a page break condition to be forced under circumstances other than the end of page. This statement initiates an immediate break to a new page. Page trailers and page headers are printed. The TRIGGER PAGE BREAK statement may not be executed if a page break is already active.

```
TRIGGER PAGE BREAK
```

The NUMPAGE= Statement

The NUMPAGE= statement allows the value of the Report Writer page counter to be changed during the execution of the report. The page counter is normally incremented by Report Writer just prior to the printing of a page header.

```
NUMPAGE= number
```

The parameter is:

number A numeric expression evaluating to an integer value between 0 and 32767.

The END REPORT Statement

The END REPORT statement terminates the active report. It triggers all trailer statements in descending level number sequence, the report trailer and lastly the page trailer.

```
END REPORT
```

The STOP REPORT Statement

The STOP REPORT statement terminates the active report. The REPORT EXIT statement is executed if the following three conditions are true: 1) the STOP REPORT was executed from the program (not from the keyboard), 2) STOP REPORT is executed in the same program environment that initiated the current report (not a subprogram or function) and 3) the REPORT EXIT execution flag evaluated to a non-zero value. In all other cases, STOP REPORT immediately terminates any further printing.

The STOP REPORT statement can be executed even if a report is not active. The only time an error will be generated is while the REPORT EXIT section is active.

```
STOP REPORT
```

Functions

The Report Writer keeps track of totals, page numbers, line numbers, break conditions and the number of detail and breaks executed. These values can be accessed through the Report Writer functions.

Report Writer functions may be accessed by any subprogram and/or function internal to the program that initiated the current report by executing a BEGIN REPORT statement.

In Chapter 6, an example report program and resultant report are given. Many of the examples are taken from this report. Note that the example is on a fold out page to allow for better referencing while you read.

The AVG Function

The AVG function returns the average for the specified expression in the TOTALS ON statement. The value returned is a cumulative average since the header statement block, containing the TOTALS ON statement, was last invoked by a break condition.

AVG (level, sequence)

The parameters are:

- level A numeric expression evaluating to an integer from 0 to 9. It associates the AVG function to a TOTALS ON statement in a header with the same level number. If level equals zero, the AVG function will reference the GRAND TOTALS ON statement.
- sequence A numeric expression evaluating to a positive integer. It corresponds to the sequential position of the desired expression in the TOTALS ON statement.

An example of this function follows.

```
70  GRAND TOTALS ON Qty*Price
   .
   .
265  REPORT TRAILER WITH 5 LINES USING R_trail;AVG(0,1)
```

The value returned is the grand total of Qty*Price divided by the number of detail lines (with number of one to nine) that have been executed.

The TOTAL Function

The TOTAL function returns the running total for the specified expression in a TOTALS ON statement. The value returned is the cumulative value since the header statement block, containing the TOTALS ON statement, was last invoked by a break condition.

TOTAL (level, sequence)

The parameters are:

- level A numeric expression evaluating to an integer from 0 to 9. It associates the TOTAL functions to a TOTALS ON statement in a header with the same level number. If level equals zero, the TOTAL function will reference the GRAND TOTALS ON statement.
- sequence A numeric expression evaluating to a positive integer. It corresponds to the sequential position of the desired expression in the TOTALS ON statement.

An example of this function follows.

```
220  HEADER 3
230   TOTALS ON Qty*Price
240  TRAILER 3 USING P_trail13;TOTAL(3,1)
```

The NUMDETAIL Function

The NUMDETAIL function returns the number of DETAIL LINE statements (with number between one and nine) executed since the header statement at the specified level was executed. The number is incremented during execution of a DETAIL LINE (1-9) statement after all breaks are serviced but before control is passed to the USING part of the statement. When a level break occurs, the number is zeroed before control is passed to the associated HEADER but remains available and unchanged in all TRAILERS.

NUMDETAIL (level)

The parameter is:

level A numeric expression that evaluates to an integer from 0 to 9. It associates the NUMDETAIL with the header statement of the same level. If set to 0, the total number of detail lines (with number between one and nine) executed since the report became active is returned.

An example of this function follows.

```
60  HEADER 1
70  TOTALS ON Qty*Price
.
.
260 TRAILER 1 USING R_trail;TOTAL(1,1)/NUMDETAIL(1)
```

The NUMBREAK Function

The NUMBREAK function returns the number of times a break condition at the specified level has occurred. The NUMBREAK counter is incremented when the break is detected which is before any header routine is activated.

NUMBREAK (level)

The parameter is:

level A numeric expression evaluating to an integer from 1 to 9. It associates the NUMBREAK function with the BREAK WHEN statement of the same level.

An example of this function follows.

```
290 REPORT TRAILER WITH 5 LINES USING R_trail;TOTAL(0,1),TOTAL(0,1)/NUMBREAK(1)
```

The OLDCV Function

The OLDCV function returns the value of the control variable as it was evaluated in the last break condition. (The control variable is the parameter "control" in the BREAK WHEN statement.) Its primary purpose is to get the correct value of the control variable in trailer routines. The value changes when a break condition occurs. The old value of the control variable is changed to the new break value after all TRAILERS have been processed and before any HEADERS are called.

OLDCV[\$] (level)

The parameters are:

- \$ The \$ indicates that the control variable is a string. Without a \$, it is assumed the control variable is numeric.
- level A numeric expression that evaluates to an integer from 1 to 9. It associates the OLDCV function with the BREAK WHEN statement of the same level containing the control variable.

An example of this function follows.

```
240 TRAILER 3 WITH 2 LINES USING P_trail3,OLDCV(3),TOTAL(3,1)
```

The NUMPAGE Function

The NUMPAGE function returns the current Report Writer page number. The Report Writer page counter is incremented just before the PAGE HEADER routine is called. If the REPORT HEADER contains a TRIGGER PAGE BREAK command, the page counter is incremented during the page break setup.

An example follows.

```
150 PAGE TRAILER USING P_trail;NUMPAGE  
:  
:  
650 P_trail: IMAGE 60X,"PAGE",2D
```

The NUMLINE function

The NUMLINE function returns the current Report Writer line count.

An example follows.

```
500 DETAIL LINE 1 USING D_line;NUMLINE,Part$,Qty
```

The LAST BREAK Function

The LAST BREAK function returns the current value of the last break condition level number detected. If the value is zero, the break was triggered by the Report Writer initialization. If the value is ten, the break was triggered by the Report Writer termination (END REPORT statement).

An example follows.

```
950 IF LAST BREAK=3 THEN GOTO 1000
```

The RWINFO Function

The general information function, RWINFO, provides a means of retrieving Report Writer information. If a report is not active, a -1 is returned.

RWINFO (integer)

Integer Value	Information Returned
1	Page size.*
2	Effective page = Page size (blank line top + blank lines bottom + lines in PAGE HEADER + lines in PAGE TRAILER).
3	Number of lines used in current page (same as NUMLINE).
4	Number of lines left in current page.*
5	Number of lines left in effective page.*
6	Page break cause flag: 0 = not caused by DETAIL LINE 1 = caused by DETAIL LINE.
7	Page count (same as Numpage).
8	Number of pages left to suppress.
9	Number of logical pages produced.
10	Same as LAST BREAK.
11	Current LEFT MARGIN.
12	Current HEADER/TRAILER level if in a break condition.

* Will return a zero if pagination is turned off (PAGE LENGTH = 0).

CHAPTER 5

Execution Hierarchy

Three statements, BEGIN REPORT, END REPORT and DETAIL LINE, control the execution of the Report Writer. These statements invoke break conditions which in turn trigger special actions.

The Report Writer has a specific hierarchical order in which it executes the break conditions:

1. Page breaks always have the highest priority. Page trailers are usually processed before page headers. Page breaks are generally triggered by the internal line counter independent of any other break condition.
2. Trailers have the second highest priority. They are processed in descending sequence from the highest level to the current break level.
3. Headers have the next priority. They are processed in ascending sequence from the current break level to the highest level.
4. A detail line has the lowest priority. It is processed after all break conditions have been serviced.

This hierarchy is shown in the following table.

Break Execution Hierarchy

1st Detail Line	Detail Line Break	End Report
Report Header	Trailer 9	Trailer 9
Page Header	:	:
Header 1	Trailer n	Trailer 1
:	Header n	Report Trailer
:	:	Page Trailer
Header 9	Header 9	

n=current break level

When the first DETAIL LINE statement is executed, the statements in column one are also executed (before the detail line is printed). When following DETAIL LINE statements (with a line not equal to zero) are executed and cause a break to occur, the statements in column two are executed. When the END REPORT statement is executed, the statements in column three are executed.

Between Trailer n and Header n, Report Writer does the following for all break levels triggered:

- Resets the value of the control variables.
- Sets the Total On counters to zero.
- Sets the NUMDETAIL counters to zero.
- Increments the break counters.

After Header 9 is executed, Report Writer does the following for Detail Lines with line greater than zero:

- Increments the detail line counter.
- Increments totals.
- Checks Print Suppression conditions (also done for line = 0).
- Checks for a Page Break condition (also done for line = 0).
- Prints the Detail Line (if no Print Suppression condition is valid) (also done for line = 0).





```
400 ! Report Execution Section
410 !
420 !
430 BEGIN REPORT Inv
440 FOR I=2 TO X
450 READ #1,I;C#
460 Div%=C#[1,2] ! Set value for BREAK 1
470 Dept%=C#[3,4] ! Set value for BREAK 3
480 Part%=C#[5,9]
490 Qty=VAL(C#[10,12])
500 Price=VAL(C#[13,17])
510 !
520 DETAIL LINE 1 USING D_line1;Part$,Qty,Price,Qty*Price
530 !
540 NEXT I
550 END REPORT
560 PRINTER IS B
570 !
580 ! Line Image Section
590 !
600 R_head: IMAGE 20X,"XYZ COMPANY INVENTORY",2/
610 !
620 P_head: IMAGE 60X,8A,2/,10X,"PART",9X,"QUANTITY",10X,"UNIT",/,9X,"NUMBER",
        BX,"ON HAND",9X,"PRICE",8X,"VALUE",/
630 P_2hd: IMAGE 9X,"=====",8X,"=====",8X,"=====",8X,"====="
640 !
650 P_trail: IMAGE 60X,"PAGE",X,2D
660 !
670 P_head1: IMAGE /,2A,2X,"DIVISION"
680 !
690 P_trail1: IMAGE ,22X,"TOTAL",X,2A,X,"DIVISION",6X,DCDDDCDDDPDD,/47X,10("-")
700 !
710 P_head3: IMAGE /
720 !
730 P_trail3: IMAGE /,22X,"TOTAL DEPT ",2A,9X,DDCDDDCDDDPDD,/,46X,"-----"
740 !
750 R_trail: IMAGE 2/,22X,"TOTAL COMPANY"10X,DCDDDCDDDPDD,/22X,"AVG PER",
        " DIVISION",7X,DCDDDCDDDPDD
755 R_2tr: IMAGE 22X,"AVG PER ITEM",11X,DCDDDCDDDPDD
760 !
770 D_line1: IMAGE 9X,8A,8X,DCDDD,5X,DDCDDDPDD,3X,DDDCDDDPDD
780 !
790 END
```



XYZ COMPANY INVENTORY

4/25/78

PART NUMBER	QUANTY ON HAND	UNIT PRICE	VALUE
=====	=====	=====	=====
AA DIVISION			
A-123	15	41.15	617.25
K-573	125	10.90	1,362.50
B-115	992	75	736.50
B-125	99	37.50	3,712.50
TOTAL DEPT 1			6,428.75

A-111	782	1.99	1,556.18
D-286	906	5.28	4,783.68
N-742	94	28.67	2,694.98
A-524	120	44	52.80
TOTAL DEPT 2			9,087.64


K-419	668	9.03	6,32.04
TOTAL DEPT 3			6,032.04
TOTAL AA DIVISION			21,548.43

BB DIVISION			
F-395	50	78.75	3,937.50
C-974	225	32	72.00
J-156	12	108.05	1,296.60
K-238	41	97.87	4,012.67
TOTAL DEPT 1			9,318.77

TOTAL BB DIVISION			9,318.77

TOTAL COMPANY			30,867.20
AVG PER DIVISION			15,433.60
AVG PER ITEM			2,374.40

PAGE 1



Example 2

When the statement SUPPRESS PRINT AT 3 is added to the report description section of the previous example, the following is the resultant output.

XYZ COMPANY INVENTORY

4/25/78

PART NUMBER	QUANTY ON HAND	UNIT PRICE	VALUE
=====	=====	=====	=====
AA DIVISION			
	TOTAL AA DIVISION		21,548.43

BB DIVISION			
	TOTAL BB DIVISION		9,318.77

	TOTAL COMPANY		30,867.20
	AVG PER DIVISION		15,433.60
	AVG PER ITEM		2,374.40

PAGE 1

Example 3

This example is a subprogram which uses data from an IMAGE/250 data base. The statements which access the data base are described in the IMAGE/250 Programming Manual. The sort statement is described in the SORT/250 Programming Manual. However, the Report Writer portions of the program can be understood without knowledge of IMAGE/250 or SORT/250.

The breaks are set on product and region. Product must have a lower break level than region since product has less frequent breaks. These breaks are shown in lines 1430 and 1440. The file which has the data must be sorted first by product then by region. This is done in line 1240.

The report description section sets up the headers, trailers and totals. The header (B in the listing and report) for the product looks up the product description and prints the product number and description every time the product changes. The trailer (C) is the total number of orders, the total amount and the average price.

The header for the region (D) lists the region every time the product or region changes. The trailer (E) is the total number of orders (the number of detail lines printed) and the total dollar amount sold.

The report header (F) is the name of the report which is printed on top of the first page. The report trailer (G) lists the grand totals: the number of orders (the number of detail lines), the amount and the average price printed on the last report page.

To have a total printed in the trailer, the TOTALS ON (or GRAND TOTALS ON) statement must be used in the header. Line 1710, the report trailer, is directly connected to line 1350, the report header.

The detail line, line 1900, prints the order number, customer, city, date and price.

The page header (H) gives the date and report name then the column headings on every page. The page trailer gives the page.

The page length, margin, level and page suppression is set up in I of the listing. These values are passed to the subprogram through the COM statements.

Set Up Data Base and Spooling

```

1010 !          RP301 - Report Writer 250 demo - produces bvci
         cle by region rpt
1030 COM Base%(8),Pselect,Pass%(8),Buff%(20(4)),Lst%(2) Cln%(
4),Dat%(8)
1040 COM INTEGER Cur_seg,menu_no,Curovly%(15)
1050 !
1060 COM I%(160),INTEGER S(0:9),Restart,Spool,Code,Msg%(80),
K%(1:8)
1070 !
1080 COM #1,Sort(1:4),Options,Level,Left,Value
1090 !
1100 DIM Name%(30)
1110 INTEGER Order_date,Product
1120 !
1130 !
1140         ON ERROR GOTO R98_error
1150         LOAD SUB "RWUTIL";7.9      !Rwhalt,Error,FNCrt
1160         ON HALT CALL Rwhalt
1170 !
1180         CURSOR (1,19)
1190         LDISP "One moment while data is being sorted."
1200         IN DATA SET "CUSTOMER" USE SKP 1,Name%,SKP 1,C
ity%,SKP 3,Order_date,SKP 1,Region%,Product
1210         IN DATA SET "OPTION" USE Order$,Option$,Option
_price
1220         ASSIGN "WORKF" TO #1
1230         WORKFILE IS #1;THREAD IS "CUSTOMER","ORDER","O
PTION"
1240         SORT BY Product,Region$,Order$,Option$
1250 !
1260         PRINTER IS Pselect
1270         IF NOT Spool THEN R05
1280         PRINTER IS "SPOOL"
1290         CURSOR (1,15)
1300         LDISP " ";
1310         CURSOR (25,10)
1320         LDISP "*** REPORT IS BEING SPOOLED ***"
1330 !
F { 1340 R05:  REPORT HEADER
    1350      GRAND TOTALS ON Option_price
    1360      PRINT SPA(27),"HP 250 REPORT WRITER DEMO"
    1370 !
I { 1380      PAGE LENGTH 66-45*(Pselect=8),2*(Pselect<>8),1
    +3*(Pselect<>8)
    1390      LEFT MARGIN Left
    1400      SUPPRESS PRINT AT Level
    1410      SUPPRESS PRINT FOR Restart PAGES
    1420 !
A { 1430      BREAK 3 WHEN Product CHANGES
    1440      BREAK 6 WHEN Region$ CHANGES
    1450 !

```

cont.

Report Description

```

1460 PAGE HEADER WITH 5 LINES USING Ph1;Dat$
1470 PRINT USING Ph2
1480 PRINT USING Ph3
1490 PRINT USING Ph4
1500 !
H { 1510 PAGE TRAILER WITH 2 LINES USING Pt1;Last$,VAL$
    (NUMPAGE)
    1520 IF (Pselect=8) AND NOT Spool THEN ON FNCrt(
Last_flag,NUMPAGE,Restart,5) GOTO R20,R90_exit
    1530 IF NOT Spool THEN R20
    1540 CURSOR (34,11)
    1550 DISP "CURRENT PAGE ";VAL$(NUMPAGE)
1560 !
1570 !
B { 1580 HEADER 3 WITH 7 LINES
    1590 TOTALS ON Option_price
    1600 DBGET (Base$,"PRODUCT",7,S(*),Lst$,Buff$,Pr
oduct)
    1610 IF S(0) THEN R95_dberror
    1620 PRINT USING Hd3;Product,Buff$[3;30]
1630 !
D { 1640 HEADER 6 WITH 4 LINES USING Hd6;Region$
    1650 TOTALS ON Option_price
1660 !
C { 1670 TRAILER 3 WITH 5 LINES USING Tr3;OLDCV(3),NUMD
    ETAIL(3),TOTAL(3,1),AVG(3,1)
1680 !
E { 1690 TRAILER 6 WITH 4 LINES USING Tr6;OLDCV$(6),NUM
    DETAIL(6),TOTAL(6,1)
1700 !
G { 1710 REPORT TRAILER WITH 5 LINES USING Rt1;NUMDETAI
    L(0),TOTAL(0,1),AVG(0,1)
    1720 Last$="LAST"
    1730 Last_flag=1
1740 !
1750 R20: END REPORT DESCRIPTION
1760 !
1770 ON KEY #8:"EXIT" GOTO R90_exit
1780 ON KEY #16 GOTO R90_exit
1790 IF NOT Spool AND (Pselect=8) THEN DISP " ";
1800 !
BEGIN REPORT R05
1810 FOR I=1 TO WFLEN(1)
1820 READ #1,I;Cnptr,Orptr,Opptr
1830 IF Cnptr=Lcnptr THEN R40
1840 Lcnptr=Cnptr
1850 DBGET (Base$,"CUSTOMER",4,S(*),Lst$,Buff$,C
nptr)
1860
1870 IF S(0) THEN R95_dberror
1880 DBGET (Base$,"OPTION",4,S(*),Lst$,Buff$,Opp
tr)
1890 IF S(0) THEN R95_dberror
1900 DETAIL LINE 1 USING D11;Order$,Name$,City$,
VAL$(Order_date MOD 100)&"/"&VAL$(INT(Order_date/100)),Optio
n_price
1910 R40: NEXT I
1920 IF NUMDETAIL(0) THEN END REPORT
1930 !

```

Report Execution

Subprogram Exit

Image Section

```
1940 R90_exit:!  
1950      ASSIGN * TO #1  
1960      STOP REPORT  
1970      LOAD "RM00"  
1980 !  
1990 R95_dberror:!  
2000      LOAD "SALES",Dberror  
2010 !  
2020 R98_error:!  
2030      OFF ERROR  
2040      OFF KEY #  
2050      CALL Rwerror(ERRM$,Base$,S(*))  
2060      PAUSE  
2070      STOP  
2080 !  
2090 !      ***** PRINT USING IMAGE STATEMENTS *****  
2100 !  
2110 Ph1:   IMAGE "DATE: ",21A,"BICYCLES BY REGION REPORT"  
2120 !  
2130 Ph2:   IMAGE 6X,"ORDER",51X,"ORDER"  
2140 !  
2150 Ph3:   IMAGE 6X,"NUMBER",11X,"CUSTOMER",19X,"CITY",8X  
2160 !      , "DATE",7X,"PRICE"  
2170 Ph4:   IMAGE 4X,"=====",X,"=====  
2180 !      =====",2X,"=====",X,"=====",2X,"=====",/  
2190 Pt1:   IMAGE /,65X,5A,"PAGE ",3A  
2200 !  
2210 Hd3:   IMAGE /,"FOR PRODUCT: ",K," - ".K,/  
2220 !  
2230 Hd6:   IMAGE "  FOR REGION: ",K,/  
2240 !  
2250 Tr3:   IMAGE /,19X,"**** TOTAL ORDERS FOR ",4D.28X,DD  
2260 !      DDD,/,19X,"**** TOTAL AMOUNT",31X,DDDDCDDD.DD,/,19X,"**** AV  
2270 Tr6:   IMAGE /,19X,"*** TOTAL ORDERS FOR REGION: ",25  
2280 !      A,DDDD,/,19X,"*** TOTAL REGION AMOUNT",25X,DDDDCDDD.DD,/  
2290 Rt1:   IMAGE 2/,19X,"***** GRAND TOTAL OF ORDERS",25X  
2300 !      ,7D,/,19X,"***** GRAND AMOUNT",30X,DDDDCDDD.DD,/,19X,"*****  
2310 D11:   IMAGE 4X,11A,31A,17A,6A,DDCDDD.DD
```

DATE: 07/10/78

F { DEMONSTRATION BICYCLE COMPANY
BICYCLES BY REGION REPORT

ORDER NUMBER	CUSTOMER	CITY	ORDER DATE	PRICE
-----------------	----------	------	---------------	-------

FOR PRODUCT: 100 - Standard Bicycle } **B**

FOR REGION: MSR

101	Noname, Joseph	Loveland	5/78	75.00
*** TOTAL ORDERS FOR REGION: MSR				1
*** TOTAL REGION AMOUNT				75.00

FOR REGION: SA } **D**

103	Hernandes, Jose	Mexico City	6/78	75.00
108	Arauja, Luciano A.	Rio de Janeiro	8/78	75.00

E { *** TOTAL ORDERS FOR REGION: SA 2
*** TOTAL REGION AMOUNT 150.00

C { **** TOTAL ORDERS FOR 100 3
**** TOTAL AMOUNT 225.00
**** AVERAGE PRICE 75.00

FOR PRODUCT: 300 - 3-Speed Bicycle

FOR REGION: FE

104	Houseman, Sean	Sidney	6/78	110.00
*** TOTAL ORDERS FOR REGION: FE				1
*** TOTAL REGION AMOUNT				110.00

**** TOTAL ORDERS FOR 300 1
**** TOTAL AMOUNT 110.00
**** AVERAGE PRICE 110.00

FOR PRODUCT: 500 - 5-Speed Bicycle

FOR REGION: AFR

105	Sono, Jomo A.	Addis Ababa	5/78	125.00
*** TOTAL ORDERS FOR REGION: AFR				1
*** TOTAL REGION AMOUNT				125.00

PAGE 1

DATE: 07/10/78

BICYCLES BY REGION REPORT

ORDER NUMBER	CUSTOMER	CITY	ORDER DATE	PRICE
FOR REGION: ESP				
100	Smith, Thomas A.	Ft. Collins	6/78	125.00
*** TOTAL ORDERS FOR REGION: ESP				1
*** TOTAL REGION AMOUNT				125.00
FOR REGION: FE				
109	Bekker, Bart	Kilbirnie	6/78	125.00
*** TOTAL ORDERS FOR REGION: FE				1
*** TOTAL REGION AMOUNT				125.00
**** TOTAL ORDERS FOR 500				3
**** TOTAL AMOUNT				375.00
**** AVERAGE PRICE				125.00
FOR PRODUCT: 1000 - 10-Speed Bicycle				
FOR REGION: EUR				
106	Heining, Heinz	Boeblingen	7/78	150.00
*** TOTAL ORDERS FOR REGION: EUR				1
*** TOTAL REGION AMOUNT				150.00
FOR REGION: MSR				
107	Dalling, Jimmy	Ft. Collins	8/78	150.00
*** TOTAL ORDERS FOR REGION: MSR				1
*** TOTAL REGION AMOUNT				150.00
FOR REGION: WSR				
102	Johnson, Sam	San Fransisco	7/78	150.00
*** TOTAL ORDERS FOR REGION: WSR				1
*** TOTAL REGION AMOUNT				150.00
**** TOTAL ORDERS FOR 1000				3
**** TOTAL AMOUNT				450.00
**** AVERAGE PRICE				150.00

PAGE 2

DATE: 07/10/78

BICYCLES BY REGION REPORT

ORDER NUMBER	CUSTOMER	CITY	ORDER DATE	PRICE
-----------------	----------	------	---------------	-------

G	***** GRAND TOTAL OF ORDERS			10
	***** GRAND AMOUNT			1,160.00
	***** GRAND AVERAGE PRICE			116.00

LAST PAGE 3

Summary of Statements and Functions

Description Statements

`BREAK level WHEN control CHANGES [BY increment]`

The `BREAK` statement establishes the criteria for determining the level break condition.

`END REPORT DESCRIPTION`

The `END REPORT DESCRIPTION` statement must be used to end the description section.

`GRAND TOTALS ON exp1[; exp2...]`

The `GRAND TOTALS ON` statement provides automatic totaling for the entire report.

`HEADER level [WITH number LINES][USING { line id
image string } [#list]]
[block statements]`

The `HEADER` statement defines what is to be done as a heading when the specified level break occurs. The `USING` parameters are the same as in a `PRINT USING` statement.

`LEFT MARGIN column`

The `LEFT MARGIN` statement sets the column in which each line of the report will begin.

`PAGE HEADER [WITH number LINES][USING { line id
image string } [#list]]
[block statements]`

The `PAGE HEADER` statement defines what is to be done at the top of every page. The `USING` parameters are the same as in a `PRINT USING` statement.


PAGE LENGTH lines per page [* blank top * blank bottom]

The PAGE LENGTH statement specifies the number of lines there are on the page. The number of blank lines to be printed at the top and bottom of the page may also be specified.

PAGE TRAILER [WITH number LINES][USING { line id
image string } [* list]]
[block statements]

The PAGE TRAILER statement defines what is to be done at the bottom of each page. If more than one line is used, that number should be specified. The USING parameter are the same as in a PRINT USING statement.

PAUSE AFTER number PAGES

The PAUSE AFTER statement causes a pause to occur after the specified number of pages has been output. The  key is pressed to resume output.

PRINT DETAIL IF condition expression

The PRINT DETAIL IF statement causes exceptional detail lines only to be printed without affecting the totaling functions.

REPORT EXIT (exec flag) [WITH number LINES][USING { line id
image string } [* list]]
[block statements]

The REPORT EXIT statement defines what action is to be taken when the report is prematurely stopped.

[label *] REPORT HEADER [WITH number LINES][USING { line id
image string } [* list]]
[block statements]

The REPORT HEADER statement begins the description section. It specifies what is to be done at the beginning of the report. The USING parameters are the same as in a PRINT USING statement.

REPORT TRAILER [WITH number LINES][USING { line id
image string } [#list]]
[block statements]

The REPORT TRAILER statement defines what is to be done at the end of the report. If more than one line is required, that number should be specified. The USING parameters are the same as in a PRINT USING statement.

SUPPRESS PRINT AT level

The SUPPRESS PRINT AT statement specifies the level of headers and trailers that will be printed. Those with equal or higher levels will not be printed.

SUPPRESS PRINT FOR number PAGES

The SUPPRESS PRINT FOR statement causes the first specified number of pages not to be printed.

TOTALS ON exp₁[* exp₂...]

The TOTALS ON statement provides automatic totaling for a break level. It immediately follows a header statement.

TRAILER level [WITH number LINES][USING { line id
image string } [#list]]
[block statements]

The TRAILER statement defines what is to be done as a trailer for the specified break level. If more than one line is required, that number should be specified. The USING parameters are the same as in a PRINT USING statement.

Execution Statements

`BEGIN REPORT line id`

The `BEGIN REPORT` statement initiates execution of a report, the description section of which is referenced by the line id.

`DETAIL LINE detail [WITH number LINES][USING { line id
image string } [list]]`

The `DETAIL LINE` statement causes all break conditions to be tested, totals to be incremented, and data to be printed. If more than one line is required for data output, that number should be specified. The `USING` parameters are the same as in a `PRINT USING` statement.

`END REPORT`

The `END REPORT` statement causes final trailers to be executed and terminates the Report Writer.

`NUMPAGE= expression`

The `NUMPAGE=` statement causes the page counter to take the specified value.

`STOP REPORT`

The `STOP REPORT` statement immediately terminates an active report. No trailing statements are printed.

`TRIGGER BREAK level`

The `TRIGGER BREAK` statement forces a break condition at the specified level.

`TRIGGER PAGE BREAK`

The `TRIGGER PAGE BREAK` statement forces a page to break.

Functions

AVG (level, sequence)

The AVG function returns the average for the specified expression in a TOTALS ON statement. The level of the TOTALS ON statement and the sequential position of the expression are specified.

NUMBREAK (level)

The NUMBREAK function returns the number of times the specified level break condition has occurred.

NUMDETAIL (level)

The NUMDETAIL function returns the number of DETAIL LINE statements that have been executed since the specified level header was last executed.

OLDCV[\$] (level)

The OLDCV function returns the value of the control variable as it was in the last level break condition. If the control variable is a string, the \$ is appended to OLDCV.

TOTAL (level, sequence)

The TOTAL function returns the running total for the specified expression in a TOTALS ON statement. The level of the TOTALS ON and the sequential position of the expression are specified.

LAST BREAK

The LAST BREAK function returns the value of the last break condition level number detected.

NUMLINE

The NUMLINE function returns the current line number to which output will go.

NUMPAGE

The NUMPAGE function returns the current page number to which output will go.

RWINFO (integer)

The RWINFO function returns Report Writer information.

APPENDIX B

Error Messages

- 250 The BEGIN REPORT statement does not reference a report header. You should check the line id specified in the parameter and the line id of the line containing the REPORT HEADER statement.
- 251 A BEGIN REPORT statement was encountered when the Report Writer was already active. The BEGIN REPORT statement must be outside the execution loop.
- 252 An END REPORT DESCRIPTION statement is missing as a terminator to the description section. This error may occur when the BEGIN REPORT is executed. If the description section precedes the execution section, the Report Writer reads the header statement then skips over any statements until the END REPORT DESCRIPTION statement. If it is missing, this error will occur. you should check the program listing carefully. Every REPORT HEADER statement must have a corresponding END REPORT DESCRIPTION statement.
- 253 A duplicate description section statement has been encountered. You should check that the level number of each header, trailer or break statement is not duplicated. All other description statements can only be used once in a description section.
- 254 The number of blank lines in the PAGE LENGTH statement is invalid. This number must be a non-negative integer and may not exceed page length minus 1.
- 255 Expression in a statement evaluates to an unacceptable value. The acceptable values for each expression can be found in the appropriate chapter.
- 256 A GRAND TOTALS ON or TOTALS ON is improperly positioned in the description section. These statements must immediately follow the header statement. Only one totals statement is allowed per header.
- 257 A. A Report Writer operation was requested while a report was not active.
B. An END REPORT statement was not executed before a subprogram terminated.
- 258 Effective page size is less than three lines. Effective page size is the number of blank lines plus the number of lines required for the page header and page trailer subtracted from the page length.
- 259 Invalid execution of a description section statement. This may be caused by a description section statement not being within the description section, or by the program branching into the description section.

- 260 Insufficient space for printed output within the current printer page. Most likely caused because the WITH number LINES parameter was too small for a header, trailer, or detail line.
- 261 Left margin specified is less than one or greater than the current printer width - 1, or is greater than 132.
- 262 A character string in BREAK WHEN control variable has a length greater than was found at the execution of a BEGIN REPORT. Refer to BREAK WHEN in Chapter 2 for a description of the control variable and its length.
- 263 A DETAIL LINE statement may not appear within the report description section.
- 264 The level parameter is out of range for a Report Writer statement. Level must be from zero to nine.
- 265 TOTALS ON or GRAND TOTALS ON statement is not active for the level requested. A TOTAL or AVG function refers to a level which has no GRAND TOTALS ON or TOTALS ON statement.
- 266 The sequence parameter is out of range for the GRAND TOTALS ON or TOTALS ON statement at the level requested.
- 267 The WITH number LINES parameter in a header, trailer, or detail line is greater than the effective page size or is negative.
- 268 The OLDCV function references a level which has no corresponding break level.
- 269 The OLDCV function does not match the data types for the control variable in a BREAK WHEN statement at the level requested. You should check that the level specified is correct and check the data types of the control variable.
- 270 The PRINTER IS statement may not be executed while the Report Writer is active.
- 271 Report Writer statement may not be used recursively.

APPENDIX C

Memory Requirements

A program which uses Report Writer statements requires a minimum of 220 bytes of User Memory. Additional memory is required for each of the following statements.

Each Statement:	Uses This Number of Bytes:
TOTALS ON	10+(8•number of expressions)
BREAK WHEN	28
numeric control variable	10+(DIM length or 18 if default- rounded up to an even number)
string control variable	8
PRINT DETAIL IF	



SALES & SERVICE OFFICES

AFRICA, ASIA, AUSTRALIA

ANGOLA
Telectra
Empresa Técnica de Equipamentos
Elétricos S A R L
R. Barbosa Rodrigues 42-1 DT
Cairo Postal 6487
Luanda
Tel: 35515 6
Cable: ELECTRA Luanda

AUSTRALIA
Hewlett-Packard Australia Pty Ltd
31-41 Joseph Street
Blackburn Victoria 3130
P.O. Box 36
Doncaster East Victoria 3109
Tel: 89-6351
Telex: 31-024
Cable: HEWPARD Melbourne
Hewlett-Packard Australia Pty Ltd
31 Bridge Street
Pymble
New South Wales 2073
Tel: 449-6566
Telex: 21561
Cable: HEWPARD Sydney
Hewlett-Packard Australia Pty Ltd
153 Greenhill Road
Parkside S.A. 5063
Tel: 272-5911
Tel: 82536 ADEL
Cable: HEWPARD ADEL
Hewlett-Packard Australia Pty Ltd
141 Stirling Highway
Nadlands W.A. 6009
Tel: 86-5455
Telex: 93859 PERTH
Cable: HEWPARD PERTH
Hewlett-Packard Australia Pty Ltd
121 Wollongong Street
Fyshwick A.C.T. 2609
Tel: 95-2733
Telex: 62650 Canberra
Cable: HEWPARD CANBERRA
Hewlett-Packard Australia Pty Ltd
5th Floor
Teachers Union Building
495-499 Boundary Street
Spring Hill 4000 Queensland
Tel: 229-1544
Cable: HEWPARD Brisbane

GUAM
Medical Pocket Calculators Only
Guam Medical Supply, Inc.
Jay Ease Building Room 210
P.O. Box 8947
Tamuning 96911
Tel: 646-8513
Cable: EARMED Guam

HONG KONG
Schmidt & Co (Hong Kong) Ltd
P.O. Box 297
Connaught Centre
39th Floor
Connaught Road Central
Hong Kong
Tel: H 255291-5
Telex: 74766 SCHMC HX
Cable: SCHMIDTCO Hong Kong

INDONESIA
Blue Star Ltd
Kasturi Buildings
Jamsilgata Rd
Bombay 400 020
Tel: 29 50 21
Telex: 001-2156
Cable: BLUEFRST
Blue Star Ltd
Saha
414 2 Vir Savarkar Marg
Prabhadev
Bombay 400 025
Tel: 45 78 87
Telex: 011-4093
Cable: FROSTBLU
Blue Star Ltd
Band Box House
Prabhadev
Bombay 400 025
Tel: 273 01
Telex: 011-3751
Cable: BLUESTAR
Blue Star Ltd
7 Hare Street
P.O. Box 506
Calcutta 700 001
Tel: 23-0131
Telex: 021-7655
Cable: BLUESTAR
Blue Star Ltd
7th & 8th Floor
Bhandari House
91 Havelock Place
New Delhi 110024
Tel: 634-772 & 635166
Telex: 031-2463
Cable: BLUESTAR
Blue Star Ltd
Blue Star House
111A Magarath Road
Bangalore 560 025
Tel: 55666
Telex: 043-430
Cable: BLUESTAR
Blue Star Ltd
Meekshi Mandiran
xxx 1678 Mahatma Gandhi Rd
Cochin 682 016
Tel: 32069 32161 32282
Tel: 0885-514
Cable: BLUESTAR
Blue Star Ltd
1-117-1
Sarajini Devi Road
Secunderabad 500 003
Tel: 701-26 70127
Cable: BLUEFRST
Telex: 015-459

JAPAN
Yokogawa Hewlett-Packard Ltd
Onashi Building
59-1 Yoyogi 1-Chome
Shibuya-ku Tokyo 151
Tel: 03-370-2281-92
Telex: 232 2024YHP MARKET
Tokyo 233-724
Cable: YHPMARKET
Yokogawa Hewlett-Packard Ltd
Chuo Bldg. 4th Floor
4-20 Nishinakajima 5-chome
Yodogawa-ku Osaka shi
Osaka 532
Tel: 06-304-6021
Yokogawa Hewlett-Packard Ltd
Nakano Building
24 Kami Sasajima-cho
Nakamura-ku Nagoya 450
Tel: 10521 571-5171
Yokogawa Hewlett-Packard Ltd
Tanigawa Building
2-24-1 Tsuyaya-cho
Kanagawa-ku
Yokohama 221
Tel: 045-312-1252
Telex: 382-3204 YHP YOK
Yokogawa Hewlett-Packard Ltd
Mito Mitsui Building
105 Chome-1 San-no-maru
Mito Ibaragi 310
Tel: 0292-25-7470
Yokogawa Hewlett-Packard Ltd
Inoue Building
134B-3 Asahi-cho 1-chome
Saitama
Atsugi Kanagawa 243
Tel: 0462-24-0452

KENYA
Technical Engineering
Services I & II Ltd
P.O. Box 18311
Nairobi
Tel: 557726 556762
Cable: PROTION
Medical Only
International Aeradio A Ltd
P.O. Box 19012
Nairobi Airport
Nairobi
Tel: 336055 56
Telex: 22201 22201
Cable: INTAFRIO Nairobi
KOREA
Samsung Electronics Co. Ltd
20th Fl. Dongbang Bldg. 250 2-KA
C.P.O. Box 2775
Taeyung-Ro Chung-Ku
Seoul
Tel: (23) 6811
Telex: 22575
Cable: ELEKSTAR Seoul
MALAYSIA
Teknik Mutu Sdn Bhd
2 Lorong 13 6A
Section 13
Petaling Jaya Selangor
Tel: 54994 54916
Telex: MA 37695
Protel Engineering
P.O. Box 1917
Lot 259 Satok Road
Kuching Sarawak
Tel: 2406
Cable: PROTELENG
MOZAMBIQUE
A.N. Gonçalves Lda
162 1. Apt. 14 A. D. Luis
Caxa Postal 10
Lourenço Marques
Tel: 27091 27114
Telex: 6-203 NEGON Mo
Cable: NEGON
NEW ZEALAND
Hewlett-Packard (N.Z.) Ltd
P.O. Box 9443
Courtenay Place
Wellington
Tel: 877-199
Cable: HEWPACK Wellington
Hewlett-Packard (N.Z.) Ltd
Paukanga Professional Centre
267 Pakuranga Highways
Box 51092
Wellington Road
Pakuranga
Tel: 569-651
Cable: HEWPACK Auckland

PHILIPPINES
The Online Advanced
Systems Corporation
Rico House
Amorsolo cor. Herrera St.
Legaspi Village Maali
Metro Manila
Tel: 85-35-81 85-34-91
Telex: 3274 DNLIN E
Analytical Medical Only
Medical Supplies N.Z. Ltd
Scientific Division
79 Carlton Gore Rd. Newmarket
P.O. Box 1234
Auckland
Tel: 75 289
Cable: DENTAL Auckland
Analytical Medical Only
Medical Supplies N.Z. Ltd
P.O. Box 1994
147-161 Tory St
Wellington
Tel: 850 799
Telex: 3858
Cable: DENTAL Wellington
Analytical Medical Only
Medical Supplies N.Z. Ltd
P.O. Box 309
239 Stannmore Road
Christchurch
Tel: 892 019
Cable: DENTAL Christchurch
Analytical Medical Only
Medical Supplies N.Z. Ltd
303 Great King Street
P.O. Box 233
Dunedin
Tel: 88-817
Cable: DENTAL Dunedin
NIGERIA
The Electronics
Instruments Ltd
N6B 770 Oyo Road
Ouseun House
P.M.B. 5402
Ibadan
Tel: 61573
Telex: 31231 TELL Nigeria
Cable: THETEL Ibadan
The Electronics Instrumenta
tions Ltd
144 Agege Motor Road Mushin
P.O. Box 6645
Lagos
Cable: THETEL Lagos
PAKISTAN
Musko & Company Ltd
Dostman Chambers
Aadular Haroon Road
Karachi 3
Tel: 511027 512927
Telex: 2894
Cable: COOPERATOR Karachi
Musko & Company Ltd
367 Satellite Town
Rawalpindi
Tel: 41524
Cable: FEMUS Rawalpindi
PHILIPPINES
The Online Advanced
Systems Corporation
Rico House
Amorsolo cor. Herrera St.
Legaspi Village Maali
Metro Manila
Tel: 85-35-81 85-34-91
Telex: 3274 DNLIN E

RHODESIA
Field Technical Sales
45 Kewin Road North
P.O. Box 3458
Salisbury
Tel: 705231 (5 lines)
Telex: RH 4122

SINGAPORE
Hewlett-Packard Singapore
(Pty) Ltd
1150 Depot Road
Alexandra P.O. Box 58
Singapore 4
Tel: 270 2355
Telex: HPSG RS 21486
Cable: HEWPACK Singapore

SOUTH AFRICA
Hewlett-Packard South Africa
(Pty) Ltd
Private Bag Wendywood
Sandton Transvaal 2144
Hewlett-Packard Centre
Daphne Street Wendywood
Sandton Transvaal 2144
Tel: 802 10408
Telex: 8-4782
Cable: HEWPACK JOHANNESBURG
Service Department
Hewlett-Packard South Africa
(Pty) Ltd
P.O. Box 39325
Graham Street 2018
451 Wyndberg Extension 3
Sandton 2001
Tel: 636-8188 5
Telex: 8-2391
Hewlett-Packard South Africa
(Pty) Ltd
P.O. Box 120
Howard Place Cape Province 7450
Pine Fork Centre Forest Drive
Pinelands Cape Province 7405
Tel: 53-7955 th 9
Telex: 57-0006
Service Department
Hewlett-Packard South Africa
(Pty) Ltd
P.O. Box 37099
Overport Durban 4067
Brady House
641 Ridge Road
Durban 4001
Tel: 88-7478
Telex: 6-7954

TAIWAN
Hewlett-Packard Far East Ltd
Taiwan Branch
39 Chung Hsiao West Road
Sec. 1 7th Floor
Taipei
Tel: 381960 4
Cable: HEWPACK TAIPEI
Hewlett-Packard Far East Ltd
Taiwan Branch
68-2 Chung Cheng 3rd Road
Kaohsiung
Tel: 07: 242318-kaohsiung
Analytical Only
San Kwang Instruments Co. Ltd
No. 20 Yung Sui Road
Taipei
Tel: 371571-4 (5 lines)
Telex: 22894 SANKWANG
Cable: SANKWANG TAIPEI

TANZANIA
Medical Only
International Aeradio (E.A.) Ltd
P.O. Box 861
Dar es Salaam
Tel: 21251 Ext. 265
Telex: 41030

THAILAND
UNIMESA Co. Ltd
Eicom Research Building
2538 Sukumvit Ave
Bangkok
Tel: 3932387 3930336
Cable: UNIMESA Bangkok

UGANDA
Medical Only
International Aeradio (E.A.) Ltd
P.O. Box 2577
Kampala
Tel: 54388
Cable: INTAFRIO Kampala

ZAMBIA
R.J. Tibury (Zambia) Ltd
P.O. Box 2792
Lusaka
Tel: 73793
Cable: ARJAYTEE Lusaka

CANADA

ALBERTA
Hewlett-Packard (Canada) Ltd
11620A - 168th Street
Edmonton T5M 3T9
Tel: (403) 452-3670
TWX 610-831-2431

BRITISH COLUMBIA
Hewlett-Packard (Canada) Ltd
210 720 Fisher St. S.E.
Calgary T2H 2H8
Tel: (403) 253-2713
TWX 610-821-6141

MANITOBA
Hewlett-Packard (Canada) Ltd
513 Century St
St. James
Winnipeg R3H 0L8
Tel: (204) 786-7581
TWX 610-671-3531

NOVA SCOTIA
Hewlett-Packard (Canada) Ltd
600 Woodmill Road
Dartmouth B3B 1L1
Tel: (902) 469-7581
TWX 610-271-4482 HFX

ONTARIO
Hewlett-Packard (Canada) Ltd
1020 Morrison Dr
Ottawa K2H 8K7
Tel: (613) 820-6483
TWX 610-563-1636

QUEBEC
Hewlett-Packard (Canada) Ltd
275 Hyman Blvd
6877 Goussier H9R 1G7
Tel: (514) 697-4232
TWX 610-422-3027
TLX 05-821521 MPCL

CENTRAL AND SOUTH AMERICA

ARGENTINA
Hewlett-Packard Argentina
S.A.
Av. Leandro N. Alem 822 - 12
100 Buenos Aires
Tel: 31-6063 4, 5, 6 and 7
Telex: 122443 AR CIGY
Cable: HEWPACK ARG

BOLIVIA
Casa Kavin S.A.
Calle Potosi 1130
P.O. Box 500
La Paz
Tel: 41530 53221
Telex: CWC BX 5298 ITT 3560082
Cable: KAVLIN

BRAZIL
Hewlett-Packard do Brasil
I.E.C. Ltda
Alameda 580 OI 807
Casília 2118
Santiago 1
Tel: 398113
Telex: 3570001 CALMET
Cable: CALMET Santiago

CHILE
Calcapin y Metcalfe Ltda
Alameda 580 OI 807
Casília 2118
Santiago 1
Tel: 398113
Telex: 3570001 CALMET
Cable: CALMET Santiago

COLOMBIA
Institución Académica
Hernán A. Langebak & Kier S.A.
Carrera 7 No. 48 75
Apartado Aéreo 6287
Bogotá, D.E.
Tel: 69-68-77
Telex: 391-21-1905 HEWP-BR
Cable: HEWPACK

COSTA RICA
Científica Costarricense S.A.
Avenida 2 Calle 5
San Pedro de Montes de Oca
Apartado 10159
San José
Tel: 24-38-20 24-08-19
Telex: 2367 GALGUR CR
Cable: GALGUR

ECUADOR
Calculators Only
Computadoras y Equipos
Electrónicos
P.O. Box 6423 CCI
Eloy Alfaro #1824 3 Piso
Quito
Tel: 453482
Telex: 02-2113 Sagita Ed
Cable: Sagita Quito

EL SALVADOR
Instrumentación y Procesamiento
Electrónico de El Salvador
Bulevar de los Héroes 11-48
San Salvador
Tel: 252787

GUATEMALA
IPESA
Avenida La Reforma 3-48
Zona 9
Guatemala City
Tel: 63627 64786
Telex: 4192 Tellerio Gu

MEXICO
Hewlett-Packard Mexicana
S.A. de C.V.
Av. Periferico Sur No. 6501
Tepic Jalisco
Mexico 23 D.F.
Tel: 905-676-4600

NICARAGUA
Roberto Terán G.
Apartado Postal 689
Edificio Terán
Managua
Tel: 54-2720
Telex: 48-71-32 48-71-84
Cable: ROTERAN Managua

PANAMA
Electrónico Balboa S.A.
P.O. Box 4929
Calle Samuel Lewis
Ciudad de Panamá
Tel: 54-2720
Telex: 3483103 Curunza
Canal Zone
Cable: ELECTRON Panama

PERU
Compañía Electro Médica S.A.
Los Flamencos 145
San Isidro Casilla 1030
Lima 1
Tel: 41-4325
Cable: ELMED Lima

PUERTO RICO
Hewlett-Packard Inter-Americanas
Puerto Rico Branch Office
Calle 272
No. 2001 Ur. Country Club
Carolina 00924
Tel: (809) 762-7255
Telex: 345 0514

URUGUAY
Pablo Ferriando S.A.
Comercial e Industrial
Avenida Itazá 2877
Casilla de Correo 370
Montevideo
Tel: 40-3102
Cable: RADIUM Montevideo

VENEZUELA
Hewlett-Packard de Venezuela
Inter-Americanas
P.O. Box 50933
Caracas 105
Los Ruces Norte
3a Transversal
Edificio Segre
Caracas 107
Tel: 35-00-11 (20 lines)
Telex: 25146 HEWPACK
Cable: HEWPACK Caracas

FOR CANADIAN AREAS NOT LISTED:
Contact Hewlett-Packard (Canada) Ltd in Mississauga

FOR AREAS NOT LISTED, CONTACT:
Hewlett-Packard Intercontinental
3200 Hillview Ave
Palo Alto, California 94304
Tel: (415) 493-1501
TWX 910-373-1267
Cable: HEWPACK Palo Alto
Tel: 034 8300 034-8493